



orders@gloriahorn.com
gloriahorn.commentsold.com/store

IQ Designer Tissue Box Cover
Follow along with our video from 4/19/2022

1. Embroidery
2. #4 Large Letters
3. 01 Letters with Flowers
4. Scroll down to the smaller size (starts at 027)
5. Choose your letter Mine is 034 H
6. Set
7. Settings Page 8 of 12 Grid: 1" Grid OK
8. Settings Page 9 of 12 Change to inches
9. Edit
10. Size
11. Resize
12. OK
13. From 2.06" x 1.74" to 1.81" x 1.54"
14. OK
15. Add
16. Menu 6
17. 02 Fancy Buttonhole
18. 001 Leaves with yellow and orange flowers
19. Set
20. Edit
21. Size
22. Resize
23. OK
24. Down to 1.07" x 2.30"
25. OK
26. Rotate
27. 10 degrees Clockwise
28. Move to where you like it.
29. OK
30. Copy
31. Mirror
32. Move to right side, opposite the first one
33. Mine ended up at 1.14" x .91"



34. The one on the left is 1.14" x -0.91"
35. OK
36. Copy
37. Rotate
38. Center
39. Rotate to 180 degrees Clockwise (so it has 40 degrees in the window) and move into place. Watch the numbers on the move screen, mine is -1.06" x -0.91"
40. OK
41. Copy
42. Mirror
43. Move into place
44. Zoom in and make sure nothing is touching.
45. I had to move my H up a little.
46. OK
47. Memory
48. Save on the machine
49. Color Change
50. Change your letter to Harvest Gold
51. 2nd Color Cream Brown
52. 3rd Color Carmine change to Tangerine
53. 5th Color Mint Green change to Lime Green
54. OK
55. Memory Save on the machine

Tissue Box Front, Top and Back:

1. Home
2. OK
3. IQ Designer
4. Shapes
5. Square
6. OK
7. Size
8. Measure your box and make your rectangle 1/2" bigger.
9. I am making mine 5" wide x 15 1/2" long
10. Center
11. OK
12. Shapes
13. Circle
14. OK
15. Measure your tissue box opening and make this circle into an oval

and 1 ½" smaller. My box opening is 4" x 2 ½" so I am making my oval 2 1/2" x 1".

16. Center
17. OK
18. Memory
19. Save on the machine
20. Line Properties
21. Straight Stitch
22. Red
23. OK
24. Line Bucket
25. Click on the rectangle and the oval
26. Fill Properties
27. Fancy Fills
28. Select
29. 013 Looks like the embroidery design.
30. OK
31. Red
32. OK
33. Fill Bucket
34. Click inside to fill it.
35. Memory Save on the machine
36. Next
37. Set
38. OK
39. Add
40. IQ Designer
41. Memory Pocket with the arrow pointing out
42. Select your outline Should be top row, second from left.
43. OK
44. Line Properties
45. No Sew
46. OK
47. Line Bucket
48. Click on the rectangle to make it not sew.
49. Line Properties
50. Zig Zag
51. Red
52. OK
53. Line Bucket
54. Click on the oval.

55. Next
56. Density
57. 110%
58. Zig Zag Width from 0.080" to 0.160"
59. Set
60. OK
61. Make sure everything is in the center: Edit Move Center
62. Select Center Select Center
63. Select the satin stitched oval
64. Edit
65. Copy
66. Move
67. Center
68. OK
69. Embroidery
70. Memory
71. Save on the machine
72. Sew this out first

Add your monogram design:

1. Home
2. Embroidery
3. Memory Pocket
4. Select your design
5. Embroidery
6. Camera
7. Scan
8. OK
9. Projector
10. Colorsort
11. GO!!

Tissue Box Sides:

1. My tissue box sides measured 5" tall x 4 1/8" wide
2. So I am making the sides 5 3/4" tall x 4 1/2" wide
3. Home
4. IQ Designer
5. Shapes
6. Square

7. OK
 8. Size
 9. 5.75" tall x 4.5 Wide
 10. Move it one inch up from center
 11. OK
 12. Copy
 13. Size
 14. Center
 15. Move 1" down from center
 16. OK
 17. Line Properties
 18. Straight stitch
 19. Red
 20. OK
 21. Line bucket
 22. Click on the lines to turn them red
 23. Fill Properties
 24. Fancy Fills
 25. Select
 26. 013
 27. OK
 28. Red
 29. OK
 30. Fill Bucket
 31. Click inside each rectangle to fill
 32. Next
 33. Preview
 34. Memory
 35. Save on the machine
 36. Set
 37. OK
 38. Embroider
- GO!!!

Follow along with the trimming and assembly instructions starting at 1
1 hour, 16 minutes

THANKS FOR WATCHING!!

